

DRIVER UTILITY PA-3251(POS-6630) 1.2

All rights reserved. Copyright 2012

Driver DVD Revision History

20120808-->Manual POS-6630_User Manual_M1.pdf Modify to POS-6630_User Manual_M2.pdf

(\POS6630 Driver1.1\Manual)

-->Add Win7,POSReady7(64-bit) driver

-->Change ID Tech OPOS driver

(POS-6630 Driver1.1\Driver\Device\Vertical Module\MSR\ID Tech MSR Driver and Utility\OPOS driver)

20120926-->Add PrinterOPOS_v2.7(\Device\Embedded Printer\LABAU\Other\Driver\OPOS Driver)

20120926-->Add Intel Wifi Driver (\Device\Wifi Module\Intel\N100 and N6205)

20140320-->Manual POS-6630_User Manual_M2.pdf Modify to POS-6630_User Manual_M3.pdf

(\POS6630 Driver1.2\Manual)

20140320-->RB MB LAN chip and TOUCH controller EOL,TO RC MB

NEW LAN-->REALTEK RTL8111F,TOUCH-->NEW EETI ETP-CP-MER4485XRU

=====
=====

1. Click on the self-extracting and self-installing setup file and answer all prompts presented.

2. You will be prompted to reboot when installation is complete.

3.The sequence of setup is Main Chip -->DotNetframework3.0(For XP) --> VGA -->ME_SW --> LAN --> SOUND --> TOUCH-->printer

=====
=====

DRIVER DVD CONTENT

=====
=====

DRIVER\----+---->\Driver\Flash BIOS\E.bat or32511P02.bat

```
|
|
+---->\Platform\XP,POSReady2009 (32-bit)\Main Chip\infinst_autol.exe
(Intel Chipset Software Installation Utility only for windows OS)
+---->\Platform\Win7,POSReady7(32-bit)\Main Chip\infinst_autol.exe
(Intel Chipset Software Installation Utility only for windows OS)
+---->\Platform\Win7,POSReady7(64-bit)\Main Chip\infinst_autol.exe
(Intel Chipset Software Installation Utility only for windows OS)
|
|
+---->\Platform\VGA\XP,POSReady2009
(32-bit)\Install_6.14.10.5436\Setup.exe(WINXP ,POS Ready 2009 DRIVER)
+---->\Platform\XP,POSReady2009 (32-bit)\DotNetframework3.0(For XP)

+---->\Platform\VGA\Win7,POSReady7(32-bit)\Install_8.15.10.2761\Setup.exe (WIN7
32bit DRIVER)

+---->\Platform\Win7,POSReady7(64-bit)\VGA\Win7_64_152612.exe(WIN7 64bit
DRIVER)
|
|
for RB MB
+---->\Platform\XP,POSReady2009(32-bit)\LAN\Realtek
RTL8111DL\RB\Setup.exe(WINXP ,POS Ready 2009 DRIVER)
+---->\Platform\Win7,POSReady7(32-bit)\LAN\Realtek
RTL8111DL\RB\Setup.exe (WIN7 32bit DRIVER)
+---->\Platform\Win7,POSReady7(64-bit)\LAN\Realtek
RTL8111DL\RB\Setup.exe \ (WIN7 64bit DRIVER)
for RC MB
+---->\Platform\XP,POSReady2009(32-bit)\LAN\Realtek
RTL8111F\RC\Setup.exe(WINXP ,POS Ready 2009 DRIVER)
+---->\Platform\Win7,POSReady7(32-bit)\LAN\Realtek
RTL8111F\RC\Setup.exe (WIN7 32bit DRIVER)
+---->\Platform\Win7,POSReady7(64-bit)\LAN\Realtek
RTL8111F\RC\Setup.exe (WIN7 64bit DRIVER)
|
|
+---->\Platform\XP,POSReady2009 (32-bit)\SOUND\Realtek
```

ALC888S\Win_XP_32bit\WDM_R266.exe (WINXP ,POS Ready 2009 DRIVER)
 +---->\Platform\Win7,POSReady7(32-bit)\SOUND\Realtek
 ALC888S\Win7_32_64bit\Vista_Win7_R266.exe (WINVISTA/7 32bit and 64bit
 DRIVER)
 +---->\Platform\Win7,POSReady7(64-bit)\SOUND\Realtek
 ALC888S\64bit_Vista_Win7_R268.exe
 |
 |
 for RB MB
 +---->\Device\Touch Screen\Win2K_XP_VISTA_7\Setup.exe
 5.11.0.9126(WINXP ,POS Ready 2009, WIN_7_32_64bit DRIVER)
 for RC MB
 +---->\Device\Touch Screen\Win2K_XP_VISTA_7\Setup.exe
 5.12.0.1204(WINXP ,POS Ready 2009, WIN_7_32_64bit DRIVER)
 |
 |
 +---->\Device\Embedded Printer\LABAU\Auto Setup\Printer Setup.exe
 (Option)
 +---->\Driver\Device\Embedded Printer\SII\Win XP_7\2inch (Option)
 +---->\Driver\Device\Embedded Printer\SII\Win XP_7\3inch (Option)
 |
 |
 +---->\Device\Vertical Module\MSR\Sysking\SKH300\USB Driver
 Installer.exe(Sysking MSR, demo AP, PS2 OPOS Driver) (Option)
 +---->\Device\Vertical Module\MSR\ID Tech\Configuration
 Software\Setup.exe
 |
 |
 +---->\Device\VFD\Labau\VFDOPOSSetup5.5\Setup.exe(demp AP ,OPOS
 Driver) (Option)
 +---->\Device\VFD\Protech(USB,OPOS Driver) (Option)
 |
 |
 +---->\Device\Embedded RFID\GIGA-TMS\V1.5
 R8\AUTORUN.EXE(Option)
 |
 |
 +---->\Driver\Device\Vertical Module\FingerPrint\Setup.exe(Option)

```
|
|
+---->\Device\Wifi Module\Spark
LAN\WPER-116GN(Optional)(WINXP ,WIN_7_32bit DRIVER)
+---->\Device\Wifi Module\Intel\N100(Optional)(WINXP ,WIN_7_32_64bit
DRIVER)
+---->\Device\Wifi
Module\Intel\N6205(Optional)(WINXP ,WIN_7_32_64bit DRIVER)
|
|
+---->\Device\3G Module\ShowModem.exe(Optional)
```

API Package\---+---->\DEMO PROJECT\

```
|
|
+---->\ProxAPI standard\
|
|
+---->\Document\
```

MANUAL\AdbeRdr930_en_US.exe (PDF File reader)

=====
=====

1. System BIOS Update

Users of AMI BIOS can use the program "AFU.bat" contained in DVD-ROM for BIOS update.

- a. This is found in DVD:\Flash\E or 32511P02
- b.For RB MB-->afudos 66300P0E.bin /p /b /n /x
- c.For RC MB-->afudos 32511P02.bin /p /b /n /x

BIOS FLASH SETUP:

a. Prepare a bootable flash drive and include DOS files: AFUDOS.EXE,AFU.BAT and "BIOS ROM file

(ex.6630xxxx.ROM)" (*the flash drive need 4MB free space.)

b. Use flash drive to boot, then type "AFU 6630XXXX.ROM" and press enter to automatically flash BIOS.

(ex. C:\>afu 66300P0E.ROM <enter>)

2. The system has LAN function (Realtek RTL8111F) that can support various network adapters. The content of the LAN driver is found as follows:

a. Windows XP_POS Ready2009 /Windows 7_32_64bit

3. The Realtek ALC888S HD Audio codec sound function enhanced in this system fully compatible with

Windows XP, Windows Vista you will find the content of the Sound driver.

a. Windows XP_POS Ready2009 /Windows 7_32_64bit

4. The Main Chip directory is contained in CD-ROM for INTEL H61 Driver

a. Windows XP_POS Ready2009 /Windows 7_32_64bit

5. The VGA interface (Intel(R) HD Graphic Driver) is embedded with our system to support

CRT display, Panel Link (optional) and TV-Out Encoder (optional). The following illustration briefly shows

you the content of VGA driver in sub-directory \VGA\

a. Windows XP_POS Ready2009 /Windows 7_32_64bit

**** Third party trademarks or brand names are the property of their owners.****

