

DRIVER UTILITY PA-3350 Driver 1.1

All rights reserved. Copyright 2014

Driver DVD Revision History

20140502-->Manual PA-3350_User Manual_M1.pdf Modify to PA-3350_User Manual_M2.pdf

(\PA-3350 Driver1.1\Manual)

20140502-->Add Manual PA-3350_Quick Guide_Q1_(A3)

20140502-->RB MB LAN chip and TOUCH controller EOL,TO RC MB

NEW LAN-->REALTEK RTL8111F,TOUCH-->NEW EETI ETP-CP-MER4485XRU

=====
=====

1. Click on the self-extracting and self-installing setup file and answer all prompts presented.

2. You will be prompted to reboot when installation is complete.

3.The sequence of setup is Main Chip -->DotNetframework3.0(For XP) --> VGA -->ME_SW --> LAN --> SOUND --> TOUCH-->printer

=====
=====

DRIVER DVD CONTENT

=====
=====

DRIVER\---->\Driver\Flash BIOS\3.bat(for RB)
 \Driver\Flash BIOS\2.bat(for RC)
 |
 |
 +---->\Platform\XP,POSReady2009 (32-bit)\Main Chip\infinst_autol.exe
(Intel Chipset Software Installation Utility only for windows OS)
 +---->\Platform\Win7,POSReady7(32-bit)\Main Chip\infinst_autol.exe
(Intel Chipset Software Installation Utility only for windows OS)
 +---->\Platform\Win7,POSReady7(64-bit)\Main Chip\infinst_autol.exe
(Intel Chipset Software Installation Utility only for windows OS)

```
|
|
+---->\Platform\VGA\XP,POSReady2009
(32-bit)\Install_6.14.10.5436\Setup.exe(WINXP ,POS Ready 2009 DRIVER)
+---->\Platform\XP,POSReady2009 (32-bit)\DotNetframework3.0(For XP)

+---->\Platform\VGA\Win7,POSReady7(32-bit)\Install_8.15.10.2761\Setup.exe (WIN7
32bit DRIVER)

+---->\Platform\Win7,POSReady7(64-bit)\VGA\Win7_64_152612.exe(WIN7 64bit
DRIVER)

|
|
for RB MB
+---->\Platform\XP,POSReady2009(32-bit)\LAN\Realtek
RTL8111DL\RB\Setup.exe(WINXP ,POS Ready 2009 DRIVER)
+---->\Platform\Win7,POSReady7(32-bit)\LAN\Realtek
RTL8111DL\RB\Setup.exe (WIN7 32bit DRIVER)
+---->\Platform\Win7,POSReady7(64-bit)\LAN\Realtek
RTL8111DL\RB\Setup.exe (WIN7 64bit DRIVER)
for RC MB
+---->\Platform\XP,POSReady2009(32-bit)\LAN\Realtek
RTL8111F\RC\Setup.exe(WINXP ,POS Ready 2009 DRIVER)
+---->\Platform\Win7,POSReady7(32-bit)\LAN\Realtek
RTL8111F\RC\Setup.exe (WIN7 32bit DRIVER)
+---->\Platform\Win7,POSReady7(64-bit)\LAN\Realtek
RTL8111F\RC\Setup.exe (WIN7 64bit DRIVER)

|
|
+---->\Platform\XP,POSReady2009 (32-bit)\SOUND\Realtek
ALC888S\Win_XP_32bit\WDM_R266.exe (WINXP ,POS Ready 2009 DRIVER)
+---->\Platform\Win7,POSReady7(32-bit)\SOUND\Realtek
ALC888S\Win7_32_64bit\Vista_Win7_R266.exe (WINVISTA/7 32bit and 64bit
DRIVER)
+---->\Platform\Win7,POSReady7(64-bit)\SOUND\Realtek
ALC888S\64bit_Vista_Win7_R268.exe

|
|
```

for RB MB
+---->\Device\Touch Screen\Win2K_XP_VISTA_7\Setup.exe
5.11.0.9126(WINXP ,POS Ready 2009, WIN_7_32_64bit DRIVER)
for RC MB
+---->\Device\Touch Screen\Win2K_XP_VISTA_7\Setup.exe
5.12.0.1204(WINXP ,POS Ready 2009, WIN_7_32_64bit DRIVER)
|
|
+---->\Device\Vertical Module\Fingerprint\DigitalPersonal\SETUP.EXE
(Option)
+---->\Device\Vertical Module\Fingerprint\U-4500B\SETUP.EXE (Option)
|
|
+---->\Device\Vertical Module\MSR\GIGA-TMS(OPOS Driver)(Option)
+---->\Device\Vertical Module\MSR\ID Tech MSR and Sysking MSR ,
demo AP , OPOS Driver(Option)
+---->\Device\Vertical Module\MSR\Protech(USB,OPOS Driver) (Option)
+---->\Device\Vertical Module\MSR\Sysking(demo AP , OPOS Driver)
(Option)
|
|
+---->\Device\VFD\Labau\VFDOPOSSetup5.5\Setup.exe(demp AP ,OPOS
Driver) (Option)

+---->\Device\VFD\Protech\MB-4103\OPOS\D04-P400-000-01-110630\MB4000_Opo
sSetup
|
|
+---->\Device\Embedded Printer\LABAU\Auto Setup\Printer Setup.exe
(Option)
+---->\Device\Embedded Printer\Protech\MB-1030\USB/OPOS
Driver(Option)
+---->\Device\Embedded Printer\Protech\MB-1011(3)OEM_SII/OPOS
Driver(Option)
+---->\Device\Embedded Printer\SII\Win XP_7\2inch (Option)
+---->\Device\Embedded Printer\SII\Win XP_7\3inch (Option)
|
|

```

+---->\Device\Embedded RFID\GIGA-TMS\V1.5
R8\AUTORUN.EXE(Optional)
|
|
+---->\Device\VFD\Labau Setup.exe(demp AP ,OPOS Driver) (Option)
+---->\Device\VFD\Protech(USB,OPOS Driver) (Option)
|
|
+---->\Device\Wifi Module\Spark
LAN\WPER-116GN(Optional)(WINXP ,WIN_7_32bit DRIVER)
+---->\Device\Wifi
Module\Intel\N6205(Optional)(WINXP ,WIN_7_32_64bit DRIVER)
|
|
+---->\Device\3G Module\ShowModem.exe(Optional)

```

```

API Package\---+---->\DEMO PROJECT\
|
|
+---->\ProxAPI standard\
|
|
+---->\Document\

```

MANUAL\AdbRdr930_en_US.exe (PDF File reader)

=====
=====

1. System BIOS Update

Users of AMI BIOS can use the program "AFU.bat" contained in CD-ROM for BIOS update.

- a. This is found in DVD:\Flash\33500P03 or 33501P02
- b. For RB MB-->afudos 33500P03.bin /p /b /n /x

c.For RC MB-->afudos 33501P02.bin /p /b /n /x

BIOS FLASH SETUP:

a. Prepare a bootable flash drive and include DOS files: AFUDOS.EXE,AFU.BAT and "BIOS ROM file

(ex.3350xxxx.ROM)" (*the flash drive need 4MB free space.)

b. Use flash drive to boot, then type "AFU 3350XXXX.ROM" and press enter to automatically flash BIOS.

(ex. C:\>afu 33500P03.ROM <enter>)

2. The system has LAN function (Realtek RTL8111F) that can support various network adapters. The content of the LAN driver is found as follows:

a. Windows XP_POS Ready2009 /Windows 7_32_64bit

3. The Realtek ALC888S HD Audio codec sound function enhanced in this system fully compatible with

Windows XP, Windows Vista you will find the content of the Sound driver.

a. Windows XP_POS Ready2009 /Windows 7_32_64bit

4. The Main Chip directory is contained in CD-ROM for INTEL H61 Driver

a. Windows XP_POS Ready2009 /Windows 7_32_64bit

5. The VGA interface (Intel(R) HD Graphic Driver) is embedded with our system to support

CRT display, Panel Link (optional) and TV-Out Encoder (optional). The following illustration briefly shows

you the content of VGA driver in sub-directory \VGA\

a. Windows XP_POS Ready2009 /Windows 7_32_64bit

**** Third party trademarks or brand names are the property of their owners.****

